

UMail 匯入自行購買的 SSL 憑證

[步驟 1] 請依照下面畫面操作。

PS:憑證產生需等待 10 秒的時間，請勿點選其他畫面。

The screenshot shows the UBLINK system settings page for generating an SSL certificate. The left sidebar contains various system management options, with '系統設定' (System Settings) highlighted. The main content area is titled '系統設定 / 設定SSL憑證' (System Settings / Set SSL Certificate). It includes a version check (3.23) and a warning to ensure the version is 3.23 or higher. Below this is a form with the following fields: Country (TW), State or Province Name (my state), Locality Name (my location), Organization (my Organization), Organizational Unit Name (my Organization unit), Common Name (mydomain.com), E-mail contact (admin@mydomain.com), and Valid days (3650). A red box highlights the '產生憑證' (Generate Certificate) button, and a '3.' is placed next to it.

[步驟 2] 請依照下面畫面操作。

This screenshot is identical to the previous one, showing the '設定SSL憑證' (Set SSL Certificate) page. However, the '產生憑證' (Generate Certificate) button is now disabled, and the '憑證管理' (Certificate Management) button is highlighted with a red box. The '3.' next to the first button is no longer present.

[步驟 3] 請依照下面畫面操作。

PS:憑證產生需等待 10 秒的時間，請勿點選其他畫面。

UBLink
version : 3.23
Max accounts : 50000
語言 : [正(繁)體中文]

郵件伺服器
郵件記錄器
郵件掃毒器
垃圾郵件處理器
郵件條件過濾器
使用者管理
LDAP
群組信件派送
其他伺服器
網路設定
系統設定

將你購買的SSL憑證內的 SSL .key檔案
用"notepad++"開啟,將內容複製貼到這個欄位
(完全取代欄位的資料)

將你購買的SSL憑證內的 ca.crt & crt_domain.crt 檔案
用"notepad++"開啟,將2個檔案內容合併,檔案內容合併沒有先後順序,但是請記得保留原始的開頭標記與結尾標記。

系統設定 / 憑證管理

您可以由此頁面取出申請檔,向第三方CA證單位提出申請,亦可由申請單位發放的證書輸入本系統,下方證書可用於 管理界面,Webmail,收發信件的SSL證書,包含pop3s,imap,smtps

根憑證證書(唯讀): 如果您的憑證非由第三方公證單位申請,可用此假憑證樣本匯入您的瀏覽器或用戶程式,如此瀏覽器會判斷憑證為安全的,通常不建議使用此方法,我們建議您正式去申請您的SSL4證書,由下方的證書管理來進行伺服器證書管理

同服務私鑰 由上一頁的憑證產生,或由您購買的憑證單位給您的檔案,請剪下內容存檔或貼入,通常這類檔案的副檔名為 .key

憑證申請書 由上一頁填寫的資訊所產生,您可以將內容剪下並存檔,第三方申請單位會需要您提供這個檔案,通常這類檔案的副檔名為 .req

憑證證書 通常由第三方的申請單位經由您提出的 .req 申請權後所核發的證書檔,您可以將核發的證書檔案內容剪貼入此

更新憑證 回到設定

[步驟 4] 請依照下面畫面操作。

UBLink
version : 3.23
Max accounts : 50000
語言 : [正(繁)體中文]

郵件伺服器
郵件記錄器
郵件掃毒器
垃圾郵件處理器
郵件條件過濾器
使用者管理
LDAP
群組信件派送
其他伺服器
網路設定
系統設定

系統設定 / 電源管理

為了系統安全,請勿直接在伺服器機器上直接按 電源按鈕直接關機,以免伺服器資料遺失,或造成系統不穩定。
若需要將伺服器關機,請在下面的電源指令輸入欄內輸入: **poweroff**
若需要將伺服器重新開機,請在下面的電源指令輸入欄內輸入: **reboot**

電源指令 3 reboot

執行

電源指令定時設定: 無 每天 每週 星期日 每月 1

時間: 3 : 30 重新開機

網路UPS: ping IP: 沒有回應,之後 60 秒,系統自動關機

狀態: normal

確定

郵件伺服器重新開機之後,請使用瀏覽器測試開啟 <https://mail.domain.com> 網頁,看是否不會再出現未授權的憑證警告訊息,若沒有再出現未授權的憑證警告訊息代表你的匯入的 SSL 憑證是有效的。