Firmware Version:	1.5.1.6
Release Type:	Normal - Upgrade recommended when convenient
Applied Models:	Vigor300B

Release Note for Vigor300B

New Features

• None.

Improvement

• Improved: Improve Web GUI Security.

Known Issue

The new firmware version 1.5.1.4 removes the support of the character "%" as the admin password to enhance the WebGUI security. If the character "%" is used as the admin password, please change the password before upgrading to the new firmware version. If the character "%" is used as the admin password and you've upgraded to the new firmware version without changing the password, please use the following CLI commands via Telnet/SSH to change the admin password.
-enable
-configure system

-admin passwd